


# PO License Server Installation On an Existing MS SQL Server


1. Create a new instance on your SQL Server with the name IIPower and sa password of ABCD1234 for that instance. (Case sensitive!)
  - a. Make sure that the **SQL Server Browser** service is set to start up **automatically**,
  - b. Make sure that the Instance has **Mixed Mode** login **enabled**,
  - c. When the installation is complete, in SQL Server Tools, SQL Server Configuration Manager, check that the **SQL Server Browser** service is **running**.
  - d. In SQL Server Network Configuration, **enable TCP/IP** for the new instance,
  - e. **Re-start the service** for the **IIPower** SQL Server.



2. On the server itself, uninstall any previous installations of POSrvTools by going to the Control Panel and Uninstalling "IIPowerOffice Server Tools"

3. On the server itself, perform a local install of POSrvTools11. (Download from <http://reticmaster.com/Files/installs/POSrvTools11.msi>)

a. When asked, select "New MSSQL Database" and click Install.




4. The Installer will run and, when complete, it will automatically run the Scripting Tool and run the correct script.


5. The scripeter will connect to the instance, create the schema, populate the relevant tables with the correct data. It will display information on its screen as it works and will display "=====END======" when it is complete.

*This is the end of the Server Installation and configuration procedure.*

6. From the first remote PC - one of the workstations with PowaMaster installed, Run PowaMaster, Click "I Agree" and then go to Help / Registration and select "Server Bulk License".



7. PowaMaster will attempt to connect to a server and fail. Click 'OK' until the Server License screen appears.




8. Make sure the radio button dot is next to 'Microsoft SQL Server,' enter your Server name in the Server Name field, leave IIPower in the Instance field and change the Database field to IIPower11 and click OK. PowaMaster will now connect to the correct server.

9. The PowaMaster Registration Screen status bar will say "First time unlock required" and generate a new serial number for the installation.

10. Email the serial number to [info@interfaces.co.za](mailto:info@interfaces.co.za) and you will be mailed an unlock code.

11. On the PowaMaster Registration screen, click the 'Unlock' button and paste the unlock code into the revealed 'Unlock Code' field. Click 'OK' and the first registration is complete.



12. On all other workstations, repeat the registration process in points 6, 7 and 8 above, and simply click on the 'OK' button. (The serial number can be ignored as long as the status bar shows licenses on the server.)

